



**COMPLIANCE TRAINING**  
**ONLINE.com**

## **Cal/OSHA, DOT HAZMAT, EEOC, EPA, HIPAA, IATA, IMDG, TDG, MSHA, OSHA, Australia WHS, and Canada OHS Regulations and Safety Online Training**

This document is provided as a training aid  
and may not reflect current laws and regulations.

Be sure and consult with the appropriate governing agencies  
or publication providers listed in the "Resources" section of our website.

[www.ComplianceTrainingOnline.com](http://www.ComplianceTrainingOnline.com)



[Facebook](#)



[LinkedIn](#)



[Twitter](#)



[Google Plus](#)



[Website](#)

# OCCUPATIONAL SAFETY AND HEALTH GUIDELINE FOR BENZENE POTENTIAL HUMAN CARCINOGEN

## INTRODUCTION

This guideline summarizes pertinent information about benzene for workers, employers, and occupational safety and health professionals who may need such information to conduct effective occupational safety and health programs. Recommendations may be superseded by new developments in these fields; therefore, readers are advised to regard these recommendations as general guidelines.

## SUBSTANCE IDENTIFICATION

- **Formula:** C<sub>6</sub>H<sub>6</sub>
- **Structure:**



- **Synonyms:** Benzol, benzole, benzolene, bicarburet of hydrogen, carbon oil, coal naphtha
- **Identifiers:** CAS 71-43-2; RTECS CY1400000; DOT 1114, label required: "Flammable Liquid"
- **Appearance and odor:** Colorless liquid with an aromatic odor

## CHEMICAL AND PHYSICAL PROPERTIES

- **Physical data**
  1. Molecular weight: 78.12
  2. Boiling point (at 760 mmHg): 80.1°C (176°F)
  3. Specific gravity (water = 1): 0.88
  4. Vapor density (air = 1 at boiling point of benzene): 2.7
  5. Melting point: 5.5°C (42°F)
  6. Vapor pressure at 20°C (68°F): 75 mmHg
  7. Solubility in water, g/100 g water at 20°C (68°F): 0.06
  8. Evaporation rate (butyl acetate = 1): 5.1
  9. Saturation concentration in air (approximate) at 25°C (77°F): 12.5% (125,000 ppm)
  10. Ionization potential: 9.25 eV
- **Reactivity**

Incompatibilities: Benzene reacts with strong oxidizers including chlorine, oxygen, and bromine with iron.

2. Hazardous decomposition products: Toxic vapors and gases (e.g., carbon monoxide) may be released in a fire involving benzene.

3. Caution: Benzene will attack some forms of plastics, coatings, and rubber.

- **Flammability**

1. Flash point: -11.1°C (12°F) (closed cup)
2. Autoignition temperature: 498°C (928°F)
3. Flammable limits in air, % by volume: Lower, 1.4; upper, 7.1
4. Extinguishant: Alcohol foam, carbon dioxide, and dry chemical extinguishants are effective. Water may be an ineffective extinguishant but may be used to cool fire-exposed containers.
5. Class IB Flammable Liquid (29 CFR 1910.106), Flammability Rating 3 (NFPA)
6. Unusual fire and explosion hazards: Benzene liquid is flammable, and its vapors can easily form explosive mixtures. Flashbacks may occur along a vapor trail.

- **Warning properties**

1. Odor threshold: 12 ppm
2. Eye irritation levels: 3,000 ppm for 0.5-1 hour
3. Other information: 3,000 ppm may irritate nose and respiratory tract.
4. Evaluation of warning properties for respirator selection: Warning properties are not considered in recommending respirators for use with carcinogens.

## EXPOSURE LIMITS

The current Occupational Safety and Health Administration (OSHA) permissible exposure limit (PEL) for benzene is 1 part of benzene per million parts of air (PPM) as a time-weighted average (TWA) concentration over an 8-hour workshift; the short-term exposure limit is 5 ppm in any 15-minute sampling period. The National Institute for Occupational Safety and Health (NIOSH) recommends that benzene be controlled and handled as a potential human carcinogen in the workplace and that exposure be reduced to the lowest feasible limit. The NIOSH recommended exposure limit (REL) is 0.1 ppm [0.32 milligrams of benzene per cubic meter of air (mg/m<sup>3</sup>)] as an 8-hour TWA and 1 ppm (3.2 mg/m<sup>3</sup>) as a ceiling in any 15-minute sampling period. The NIOSH REL is the lowest con-

U.S. DEPARTMENT OF HEALTH AND HUMAN SERVICES  
Public Health Service Centers for Disease Control  
National Institute for Occupational Safety and Health  
Division of Standards Development and Technology Transfer

centration detectable by current NIOSH-validated sampling and analytical methods. The American Conference of Governmental Industrial Hygienists (ACGIH) has designated benzene as an A2 substance (suspected human carcinogen) having an assigned threshold limit value (TLV®) of 10 ppm (30 mg/m<sup>3</sup>) as a TWA for a normal 8-hour workday and a 40-hour workweek.

**Table 1.—Occupational exposure limits for benzene**

	Exposure limits	
	ppm	mg/m <sup>3</sup>
OSHA PEL TWA	1	—
Short-term exposure limit (15 min)	5	—
NIOSH REL (Ca)* TWA	0.1	0.32
Ceiling (15 min)	1	3.2
ACGIH TLV® TWA (A2)†	10	30

\* (Ca): NIOSH recommends treating as a potential human carcinogen.

†(A2): Suspected human carcinogen.

## HEALTH HAZARD INFORMATION

### • Routes of exposure

Benzene may cause adverse health effects following exposure via inhalation, ingestion, or dermal or eye contact.

### • Summary of toxicology

1. *Effects on animals:* Acute inhalation of benzene by rats, mice, or rabbits caused narcosis, spontaneous heart contractions (ventricular fibrillation), and death due to respiratory paralysis. Subchronic inhalation of benzene by rats produced decreased white blood cell counts, decreased bone marrow cell activity, increased red blood cell activity, and cataracts. In rats, chronic inhalation or oral administration of benzene produced cancers of the liver, mouth, and Zymbal gland. Inhalation of benzene by pregnant rats caused retardation of fetal development and increased fetal mortality.

2. *Effects on humans:* Acute inhalation exposure of benzene has caused nerve inflammation (polyneuritis), central nervous system depression, and cardiac sensitization. Chronic exposure to benzene has produced anorexia and irreversible injury to the blood-forming organs; effects include aplastic anemia and leukemia.

### • Signs and symptoms of exposure

1. *Short-term (acute):* Exposure to benzene can cause dizziness, euphoria, giddiness, headache, nausea, staggering gait, weakness, drowsiness, respiratory irritation, pulmonary edema and pneumonia, gastrointestinal irritation, convulsions, and paralysis. Benzene can also cause irritation to the skin, eyes, and mucous membranes.

2. *Long-term (chronic):* Exposure to benzene can cause fatigue, nervousness, irritability, blurred vision, and labored breath-

ing. Repeated skin contact can cause redness, blistering, and dry, scaly dermatitis.

## RECOMMENDED MEDICAL PRACTICES

### • Medical surveillance program

Workers with potential exposures to chemical hazards should be monitored in a systematic program of medical surveillance intended to prevent or control occupational injury and disease. The program should include education of employers and workers about work-related hazards, placement of workers in jobs that do not jeopardize their safety and health, earliest possible detection of adverse health effects, and referral of workers for diagnostic confirmation and treatment. The occurrence of disease (a "sentinel health event," SHE) or other work-related adverse health effects should prompt immediate evaluation of primary preventive measures (e.g., industrial hygiene monitoring, engineering controls, and personal protective equipment). A medical surveillance program is intended to supplement, not replace, such measures.

A medical surveillance program should include systematic collection and epidemiologic analysis of relevant environmental and biologic monitoring, medical screening, morbidity, and mortality data. This analysis may provide information about the relatedness of adverse health effects and occupational exposure that cannot be discerned from results in individual workers. Sensitivity, specificity, and predictive values of biologic monitoring and medical screening tests should be evaluated on an industry-wide basis prior to application in any given worker group. Intrinsic to a surveillance program is the dissemination of summary data to those who need to know, including employers, occupational health professionals, potentially exposed workers, and regulatory and public health agencies.

### • Preplacement medical evaluation

Prior to placing a worker in a job with a potential for exposure to benzene, the physician should evaluate and document the worker's baseline health status with thorough medical, environmental, and occupational histories, a physical examination, and physiologic and laboratory tests appropriate for the anticipated occupational risks. These should concentrate on the function and integrity of the eyes, skin, liver, and respiratory, nervous, and hematopoietic (blood-cell-forming) systems. The physician should obtain baseline values for the complete blood count and a stained differential count of all blood cell types. Medical surveillance for respiratory disease should be conducted by using the principles and methods recommended by NIOSH and the American Thoracic Society (ATS).

A preplacement medical evaluation is recommended in order to detect and assess preexisting or concurrent conditions which may be aggravated or result in increased risk when a worker is exposed to benzene at or below the NIOSH REL. The examining physician should consider the probable frequency, intensity, and duration of exposure, as well as the nature and degree of the condition, in placing such a worker. Such conditions, which should not be regarded as absolute contraindi-

cations to job placement, include a history of chronic skin disease, concurrent dermatitis, or mild non-hemolytic anemia (e.g., mild iron-deficiency anemia).

• **Periodic medical screening and/or biologic monitoring**

Occupational health interviews and physical examinations should be performed at regular intervals. Additional examinations may be necessary should a worker report symptoms that may be attributed to exposure to benzene. The interviews, examinations, and appropriate medical screening and/or biologic monitoring tests should be directed at identifying an excessive decrease or adverse trend in the integrity and physiologic function of the skin, liver, and respiratory, nervous, and hematopoietic (blood-cell-forming) systems as compared to the baseline status of the individual worker or to expected values for a suitable reference population. The following tests should be used and interpreted according to standardized procedures and evaluation criteria recommended by NIOSH and the ATS: standardized questionnaires and tests of lung function.

• **Medical practices recommended at the time of job transfer or termination.**

The medical, environmental, and occupational history interviews, the physical examination, and selected physiologic and laboratory tests which were conducted at the time of placement should be repeated at the time of job transfer or termination. Any changes in the worker's health status should be compared to those expected for a suitable reference population. Because occupational exposure to benzene may cause diseases of prolonged induction-latency, the need for medical surveillance may extend well beyond termination of employment.

• **Sentinel health events**

1. Acute SHE's include: Acute myeloid leukemia and contact and/or allergic dermatitis.
2. Delayed-onset SHE's include: Decrease in the number (neutropenia) or absence (agranulocytosis) of certain white blood cells in the peripheral circulation and/or in the bone marrow (aplastic anemia) and cancer of the red blood cells (erythroleukemia).

## MONITORING AND MEASUREMENT PROCEDURES

• **TWA exposure evaluation**

Measurements to determine worker exposure to benzene should be taken so that the TWA exposure is based on a single entire workshift sample or an appropriate number of consecutive samples collected during the entire workshift. Under certain conditions, it may be appropriate to collect several short-term interval samples (up to 30 minutes each) to determine the average exposure level. Air samples should be taken in the worker's breathing zone (air that most nearly represents that inhaled by the worker).

• **Ceiling concentration evaluation**

Measurements to determine worker exposure should be taken during periods of maximum expected airborne concentrations of benzene. Each measurement to determine the NIOSH REL (ceiling exposure) in the worker's breathing zone (air that most nearly represents that inhaled by the worker) should consist of a 15-minute sample. A minimum of three measurements

should be taken during one workshift, and the highest of all measurements taken is an estimate of the worker's exposure. If the periods of maximum exposure are not clearly defined, a statistical procedure which can be used as a peak exposure detection strategy is given in the *Occupational Exposure Sampling Strategy Manual*.

• **Method**

Sampling and analysis may be performed by collecting benzene vapors with charcoal tubes followed by desorption with carbon disulfide and analysis by gas chromatography. Direct-reading devices calibrated to measure benzene may also be used if available. A detailed sampling and analytical method for benzene may be found in the *NIOSH Manual of Analytical Methods* (method number 1500).

## PERSONAL PROTECTIVE EQUIPMENT

Chemical protective clothing (CPC) should be selected after utilizing available performance data, consulting with the manufacturer, and then evaluating the clothing under actual use conditions.

Workers should be provided with and required to use CPC, gloves, and other appropriate protective clothing necessary to prevent skin contact with benzene.

## SANITATION

Clothing which is contaminated with benzene should be removed immediately and placed in sealed containers for storage until it can be discarded or until provision is made for the removal of benzene from the clothing. If the clothing is to be laundered or cleaned, the person performing the operation should be informed of benzene's hazardous properties. Reusable clothing and equipment should be checked for residual contamination before reuse or storage.

A change room with showers, washing facilities, and lockers that permit separation of street and work clothes should be provided.

Workers should be required to shower following a workshift and prior to putting on street clothes. Clean work clothes should be provided daily.

Skin that becomes contaminated with benzene should be promptly washed with soap and water.

Workers who handle benzene should wash their faces, hands, and forearms thoroughly with soap and water before eating, smoking, or using toilet facilities.

The storage, preparation, dispensing, or consumption of food or beverages, the storage or application of cosmetics, the storage or use of smoking materials, or the storage or use of products for chewing should be prohibited in work areas.

## COMMON OPERATIONS AND CONTROLS

Common operations in which exposure to benzene may occur and control methods which may be effective in each case are listed in Table 2.

**Table 2.—Operations and methods of control for benzene**

Operations	Controls
During the manufacture and processing of benzene; during use as a raw material in the production of aromatic compounds and derivatives	Process enclosure, local exhaust ventilation, personal protective equipment
During the use of chemicals in which benzene may be an impurity (e.g., naphthas, toluene, xylene)	Process enclosure, local exhaust ventilation, personal protective equipment
During the manufacture and use of motor fuel blends in which benzene is used as an ingredient; during use as an extracting solvent	Process enclosure (when possible), local exhaust ventilation, personal protective equipment, material substitution
During the preparation and use of paint and varnish removers, rubber cements, and lacquers	Process enclosure (when possible), local exhaust ventilation, personal protective equipment, material substitution

## EMERGENCY FIRST AID PROCEDURES

In the event of an emergency, remove the victim from further exposure, send for medical assistance, and initiate emergency procedures.

### • Eye exposure

Where there is any possibility of a worker's eyes being exposed to benzene, an eye-wash fountain should be provided within the immediate work area for emergency use.

If benzene gets into the eyes, flush them immediately with large amounts of water for 15 minutes, lifting the lower and upper lids occasionally. Get medical attention as soon as possible. Contact lenses should not be worn when working with this chemical.

### • Skin exposure

Where there is any possibility of a worker's body being exposed to benzene, facilities for quick drenching of the body should be provided within the immediate work area for emergency use.

If benzene gets on the skin, wash it immediately with soap and water. If benzene penetrates the clothing, remove the clothing immediately and wash the skin with soap and water. Get medical attention promptly.

### • Rescue

If a worker has been incapacitated, move the affected worker from the hazardous exposure. Put into effect the established emergency rescue procedures. Do not become a casualty. Understand the facility's emergency rescue procedures and know the locations of rescue equipment before the need arises.

## SPILLS AND LEAKS

Workers not wearing protective equipment and clothing should be restricted from areas of spills or leaks until cleanup has been completed.

If benzene is spilled or leaked, the following steps should be taken:

1. Remove all ignition sources.
2. Ventilate area of spill or leak.
3. For small quantities of liquids containing benzene, absorb on paper towels and place in an appropriate container.
4. Large quantities of liquids containing benzene may be absorbed in vermiculite, dry sand, earth, or a similar material and placed in an appropriate container.
5. Liquids containing benzene may be collected by vacuuming with an appropriate system. If a vacuum system is used, there should be no sources of ignition in the vicinity of the spill, and flashback prevention devices should be provided.

## WASTE REMOVAL AND DISPOSAL

U.S. Environmental Protection Agency, Department of Transportation, and/or state and local regulations shall be followed to assure that removal, transport, and disposal are in accordance with existing regulations.

## RESPIRATORY PROTECTION

It must be stressed that the use of respirators is the least preferred method of controlling worker exposure and should not normally be used as the only means of preventing or minimizing exposure during routine operations. However, there are some exceptions for which respirators may be used to control exposure: when engineering and work practice controls are not technically feasible, when engineering controls are in the process of being installed, or during emergencies and certain maintenance operations including those requiring confined-space entry (Table 3).

In addition to respirator selection, a complete respiratory protection program should be instituted which as a minimum complies with the requirements found in the OSHA Safety and Health Standards, 29 CFR 1910.134. A respiratory protection program should include as a minimum an evaluation of the worker's ability to perform the work while wearing a respirator, the regular training of personnel, fit testing, periodic environmental monitoring, maintenance, inspection, and cleaning. The implementation of an adequate respiratory protection program, including selection of the correct respirators, requires that a knowledgeable person be in charge of the program and that the program be evaluated regularly.

Only respirators that have been approved by the Mine Safety and Health Administration (MSHA, formerly Mining Enforcement and Safety Administration) and by NIOSH should be used. **Remember! Air-purifying respirators will not protect from oxygen-deficient atmospheres.**

## BIBLIOGRAPHY

- American Conference of Governmental Industrial Hygienists: *TLVs® Threshold Limit Values and Biological Exposure Indices for 1987-88*, Cincinnati, 1987.
- American Industrial Hygiene Association: "Benzene" (rev. 1978), *Hygienic Guide Series*, Detroit, 1978.
- American Lung Association of San Diego and Imperial Counties: "Taking the Occupational History," *Annals of Internal Medicine*, 99:641-651, November 1983.
- Amoores, J.E., and Hautala, E.: "Odor as a Chemical Safety Factor: Odor Thresholds Compared with Threshold Limit Values and Volatilities for 214 Industrial Chemicals in Air and Water Dilution," *Journal of Applied Toxicology*, 3:272-290, 1983.
- Baier, E.J., Deputy Director, National Institute for Occupational Safety and Health, Center for Disease Control, Public Health Service, Department of Health, Education, and Welfare: *Statement before the Department of Labor, Occupational Safety and Health, Public Hearing on the Occupational Standard for Benzene*, July 25-26, 1977.
- Clayton, G.D., and Clayton, F.E. (eds.): *Toxicology*, Vol. IIB of *Patty's Industrial Hygiene and Toxicology* (3rd rev. ed.), John Wiley & Sons, Inc., New York, 1981.
- *Code of Federal Regulations*, U.S. Department of Labor, Occupational Safety and Health Administration, 29 CFR 1910.106, 1910.134, 1910.1000, OSHA 2206, revised July 1, 1986.
- *Code of Federal Regulations*, U.S. Department of Transportation, 49 CFR 172.101, Transportation 49, revised October 1, 1982.
- Goldman, R.H., and Peters, J.M.: "The Occupational and Environmental Health History," *Journal of the American Medical Association*, 246:2831-2836, 1981.
- Halperin, W.E., Ratcliffe, J., Frazier, T.M., Wilson, L., Becker, S.P., and Shulte, P.A.: "Medical Screening in the Workplace: Proposed Principles," *Journal of Occupational Medicine*, 28(8):547-552, 1986.
- Hankinson, J.L.: "Pulmonary Function Testing in the Screening of Workers: Guidelines for Instrumentation, Performance, and Interpretation," *Journal of Occupational Medicine*, 28(10):1081-1092, 1986.
- Hawley, G.G.: *The Condensed Chemical Dictionary* (10th ed.), Litton Educational Publishing Inc., New York, 1981.
- International Agency for Research on Cancer: *IARC Monographs on the Evaluation of the Carcinogenic Risk of Chemicals to Humans, Some Industrial Chemicals and Dyestuffs*, Vol. 29, Lyon, France, 1982.
- Leidel, N.A., Busch, K.A., and Lynch, J.R.: *Occupational Exposure Sampling Strategy Manual*, U.S. Department of Health, Education, and Welfare, Public Health Service, Center for Disease Control, National Institute for Occupational Safety and Health, DHEW (NIOSH) Publication No. 77-173, Cincinnati, 1977.
- Levy, B.S., and Wegman, D.H. (eds.): *Occupational Health: Recognizing and Preventing Work-Related Disease*, Little, Brown and Company, Boston, 1983.
- National Fire Protection Association: *National Fire Codes®*, (Vol. 13), Quincy, Massachusetts, 1983.
- National Institute for Occupational Safety and Health, U.S. Department of Health, Education, and Welfare, Public Health Service, Center for Disease Control: *Criteria for a Recommended Standard . . . Occupational Exposure to Benzene*, HSM (NIOSH) Publication No. 74-137, Cincinnati, 1974.
- National Institute for Occupational Safety and Health, U.S. Department of Health, Education, and Welfare, Public Health Service, Center for Disease Control: *Revised Recommendation for an Occupational Exposure Standard for Benzene*, Cincinnati, 1976.
- National Institute for Occupational Safety and Health, U.S. Department of Health and Human Services, Public Health Service, Centers for Disease Control: *NIOSH Manual of Analytical Methods* (3rd ed., Vol. 1), Eller, P.M. (ed.), DHHS (NIOSH) Publication No. 84-100, Cincinnati, 1984.
- National Institute for Occupational Safety and Health, U.S. Department of Health and Human Services, Public Health Service, Centers for Disease Control: *Registry of Toxic Effects of Chemical Substances* (Microfiche Edition), Sweet, D.V., and Lewis, R.J. (eds.), Cincinnati, April 1985.
- Proctor, N.H., and Hughes, J.P.: *Chemical Hazards of the Workplace*, J.B. Lippincott Company, Philadelphia, 1978.
- Rom, W.N. (ed.): *Environmental and Occupational Medicine*, Little, Brown and Company, Boston, 1983.
- Rothstein, M.A.: *Medical Screening of Workers*, Bureau of National Affairs, Washington, DC, 1984.
- Rutstein, D.D., Mullan, R.J., Frazier, T.M., Halperin, W.E., Melius, J.M., and Sestito, J.P.: "Sentinel Health Events (Occupational): A Basis for Physician Recognition and Public Health Surveillance," *American Journal of Public Health*, 73:1054-1062, 1983.
- Sax, N.I. (ed.): *Dangerous Properties of Industrial Materials* (6th ed.), Van Nostrand Reinhold Company, New York, 1984.
- U.S. Department of Transportation, Coast Guard: *CHRIS Hazardous Chemical Data*, GPO Stock No. 050-012-00147-2, 1978.
- Weast, R.C. (ed.): *CRC Handbook of Chemistry and Physics* (64th ed.), CRC Press, Inc., Boca Raton, Florida, 1983.
- Windholz, M. (ed.): *The Merck Index* (10th ed.), Merck & Co., Inc., Rahway, New Jersey, 1983.

**Table 3.—Respiratory protection for benzene**

<b>Condition</b>	<b>Minimum respiratory protection*</b>
Any detectable concentration	Any self-contained breathing apparatus with a full facepiece and operated in a pressure-demand or other positive pressure mode  Any supplied-air respirator with a full facepiece and operated in a pressure-demand or other positive pressure mode in combination with an auxiliary self-contained breathing apparatus operated in a pressure-demand or other positive pressure mode
Planned or emergency entry into environments containing unknown or any detectable concentration	Any self-contained breathing apparatus with a full facepiece and operated in a pressure-demand or other positive pressure mode  Any supplied-air respirator with a full facepiece and operated in a pressure-demand or other positive pressure mode in combination with an auxiliary self-contained breathing apparatus operated in a pressure-demand or other positive pressure mode
Firefighting	Any self-contained breathing apparatus with a full facepiece and operated in a pressure-demand or other positive pressure mode
Escape only	Any air-purifying full facepiece respirator (gas mask) with a chin-style or front- or back-mounted organic canister  Any appropriate escape-type self-contained breathing apparatus

\* Only NIOSH/MSHA-approved equipment should be used.